

PSA 5.1.02 Release Notes

The PSA 5.1.02 Release Note is applicable to the PSA-3000 and PVA-3000 family of test instruments.

Summary

The PSA 5.1.02 release contains one critical bug fix. In every other respect, PSA 5.1.02 is identical to the PSA 5.1.01 release and the associated PSA 5.1.01 Release Notes apply.

PSA 5.0.02 Bug Fixes

Software Entity	Impact	Feature
PSA Interactive 5.1	Major	<p>The new PSE Conformance Test tab menu in PSA Interactive includes a critical bug whereby the Type-2, 30W radiobutton control is essentially ignored when testing 2-Pair PSE's. Therefore all testing is done with Type-1, 15.4W emulation regardless of radiobutton selection.</p> <p>Also, when testing Type-3, 2-Pair PSE's, the Type-2, 30W radiobutton is disabled for all Type-3 2-Pair PSE's. It should be enabled if the High Power Grant Method for the PSE-under-test is PHY, LLDP, or PHY+LLDP.</p> <p>PSA 5.1.02 corrects both of these issues.</p>